

PowerShell Networking Guide





Windows PowerShell Networking Guide

The DevOps Collective, Inc.

This book is for sale at http://leanpub.com/windowspowershellnetworkingguide

This version was published on 2018-10-28



This is a Leanpub book. Leanpub empowers authors and publishers with the Lean Publishing process. Lean Publishing is the act of publishing an in-progress ebook using lightweight tools and many iterations to get reader feedback, pivot until you have the right book and build traction once you do.

© 2016 - 2018 The DevOps Collective, Inc.

Also By The DevOps Collective, Inc.

Creating HTML Reports in Windows PowerShell

A Unix Person's Guide to PowerShell

The Big Book of PowerShell Error Handling

DevOps: The Ops Perspective

Ditch Excel: Making Historical and Trend Reports in PowerShell

Secrets of PowerShell Remoting

The Big Book of PowerShell Gotchas

The Monad Manifesto, Annotated

Why PowerShell?

The PowerShell + DevOps Global Summit Manual for Summiteers

Why PowerShell? (Spanish)

Secrets of PowerShell Remoting (Spanish)

DevOps: The Ops Perspective (Spanish)

The Monad Manifesto: Annotated (Spanish)

Creating HTML Reports in PowerShell (Spanish)

The Big Book of PowerShell Gotchas (Spanish)

The Big Book of PowerShell Error Handling (Spanish)

DevOps: WTF?

PowerShell.org: History of a Community


Contents

PowerShell Networking Guide	1
Windows PowerShell Basics - Introduction	2
Windows PowerShell Basics - Security issues with Windows PowerShell	
Windows PowerShell Basics - Using PowerShell cmdlets	7
Windows PowerShell Basics - Supplying options for cmdlets	
Windows PowerShell Basics - Using command line utilities	. 19
Windows PowerShell Basics - Working with help options	. 20
Windows PowerShell Basics - Working with modules	. 2 1
Working with Network adapters	22
Identifying network adapters Using raw WMI to identify network adapters Using NetSh Using PowerShell on Windows 8 or above	24
Enabling and disabling network adapters	
Renaming the network adapter	39
Finding connected network adapters	43

CONTENTS

Requires -Version 2.0	. 46
>	. 47
*** Entry point to script ***	
Network Adapter power settings	. 52
Getting Network Statistics	57
Resources Web Resources	. 68

PowerShell Networking Guide



This guide is released under the Creative Commons Attribution-NoDerivs 3.0 Unported License. The authors encourage you to redistribute this file as widely as possible, but ask that you do not modify the document.

PowerShell can be used to manage the networking aspects of your server and client computers.

Was this book helpful? The author(s) kindly ask(s) that you make a tax-deductible (in the US; check your laws if you live elsewhere) donation of any amount to The DevOps Collective¹ to support their ongoing work.

Check for Updates! Our ebooks are often updated with new and corrected content. We make them available in three ways:

- Our main, authoritative GitHub organization², with a repo for each book. Visit https://github.com/devops-collective-inc/
- Our GitBook page³, where you can browse books online, or download as PDF, EPUB, or MOBI. Using the online reader, you can link to specific chapters. Visit https://www.gitbook.com/@devopscollective
- On LeanPub⁴, where you can download as PDF, EPUB, or MOBI (login required), and "purchase" the books to make a donation to DevOps Collective. You can also choose to be notified of updates. Visit https://leanpub.com/u/devopscollective

GitBook and LeanPub have slightly different PDF formatting output, so you can choose the one you prefer. LeanPub can also notify you when we push updates. Our main GitHub repo is authoritative; repositories on other sites are usually just mirrors used for the publishing process. GitBook will usually contain our latest version, including not-yet-finished bits; LeanPub always contains the most recent "public release" of any book.

¹https://devopscollective.org/donate/

²https://github.com/devops-collective-inc

³https://www.gitbook.com/@devopscollective

⁴https://leanpub.com/u/devopscollective

Windows PowerShell Basics - Introduction

Windows PowerShell is not new technology. Windows PowerShell 4.0 ships in Windows 8.1 and in Windows Server 2012 R2, it has therefore been around for a while. Windows PowerShell is an essential admin tool designed specifically for Windows administration. By learning to use Windows PowerShell, network administrators quickly gain access to information from Windows Management Instrumentation, Active Directory and other essential sources of information. Additionally, Microsoft added Windows PowerShell support to the Common Criteria requirements for shipping enterprise applications. Therefore, to manage Microsoft Exchange, Azure, SQL Server, and others one needs to know and to understand how to use Windows PowerShell. In the networking world, this knowledge is also a requirement for managing DNS, DHCP, Network Adapters, and other components.

So what are the basics of Windows PowerShell that I need to know?

Windows PowerShell comes in two flavors - the first is an interactive console (sort of like a KORN or a BASH console in the UNIX world) built into the Windows command prompt. The Windows PowerShell console makes it simple to type short commands and to receive sorted, filtered, formatted results. These results easily display to the console, but can redirect to XML, CSV, or text files. The Windows PowerShell console offers several advantages such as speed, low memory overhead, and a comprehensive transcription service that records all commands and command output.

There is also the Windows PowerShell ISE. The Windows PowerShell ISE is an Integrated Scripting Environment, but this does not mean you must use it to write scripts. In fact, many Windows PowerShell users like to write their code in the Windows PowerShell ISE to take advantage of the color syntax-highlighting, drop down lists, and automatic parameter revelation features. In addition, the Windows PowerShell ISE has a feature, called the _Show Command Add-On _that permits using a mouse to create Windows PowerShell commands from a graphical environment. Once created, the command either runs directly, or adds to the script pane (the choice is up to you).

Working with Windows PowerShell

On Windows 8 or on Windows Server 2012 Windows PowerShell 3.0 already exists. On Windows 8.1 Windows PowerShell 4.0 is installed, as it is on Windows Server 2012 R2. Windows 8 (and 8.1) you

only need to type the first few letters of the word PowerShell on the Start screen before Windows PowerShell appears as an option. The figure appearing here illustrates this point. I only typed _pow _before the Start screen search box changes to offer Windows PowerShell and an option.



image001.png

Because navigating to the Start screen and typing _pow _each time I want to launch Windows PowerShell is a bit cumbersome, I prefer to Pin the Windows PowerShell console (and the Windows PowerShell ISE) to both the Start page and to the Windows desktop taskbar. This technique of pinning shortcuts to the applications provides single click access to Windows PowerShell from wherever I may be working.




image003.png

On Windows Server 2012 (and on Windows Server 2012 R2), it is not necessary to go through the Start screen / Search routine because an icon for the Windows PowerShell console exists by default on the taskbar of the desktop.

NOTE: The Windows PowerShell ISE (the script editor) does not exist by default on Windows Server 2012 and Windows Server 2012 R2. You add the Windows PowerShell ISE as a feature.

Windows PowerShell Basics - Security issues with Windows PowerShell

There are two ways of launching Windows PowerShell - as an administrator and as a normal user. It is a best practice when starting Windows PowerShell to start it with minimum rights. On Windows 8 (and on Windows 7) this means simply clicking on the Windows PowerShell icon. It opens as a non-elevated user (even if you are logged on with Administrative rights). On Windows Server 2012, Windows PowerShell automatically launches with the rights of the current user and therefore if you are logged on as a Domain Administrator, the Windows PowerShell console launches with Domain Administrator rights.

Running as a normal (non-elevated) user

Because Windows PowerShell adheres to Windows security constraints, a user of Windows PowerShell cannot do anything that the user account does not have permission to do. Therefore, if you are a non-elevated normal user, you will not have rights to do things like install printer drivers, read from the Security log, or change system time.

Even if you are an administrator on the local Windows 8 (or Windows 7) desktop machine and you do not launch Windows PowerShell with admin rights, you will get errors when attempting to do things like see the configuration of your disk drives. This command and associated error appears here. PS C:\> get-disk get-disk : Access to a CIM resource was not available to the client. At line:1 char:1 + get-disk + ~~~~~~~ + CategoryInfo : PermissionDenied: (MSFT_Disk:ROOT/Microsoft/Windows/S torage/MSFT_Disk) [Get-Disk], CimException + FullyQualifiedErrorId : MI RESULT 2,Get-Disk TIP: There is an inconsistency with errors arising when attempting to run cmdlets that require elevated rights. For example, when inside a non-elevated Windows PowerShell console, the error from Get-Disk is _Access to a CIM resource was not available to the client. _The error from Stop-Service is _Cannot open xxx service on computer. _While the Get-VM cmdlets simply returns no information (an no error). Therefore, as a first step in troubleshooting, check for console rights.

Launching PowerShell with Admin rights

When you need to perform tasks that require Admin rights, you need to start the Windows PowerShell console with admin rights. To do this, right click on the Windows PowerShell icon (from either the one pinned to the task bar, the start page, or even from the one found from the Start / Search page) and select the _Run As Administrator _option from the action menu. The great thing about this technique is that it permits launching either the Windows PowerShell console (the first item on the menu) as an Administrator, or from the same screen you can launch the Windows PowerShell ISE as an Administrator. This appears in the figure that follows.




image005.png

Once you launch the Windows PowerShell console with admin rights, the User Account Control dialog box appears seeking permission to allow Windows PowerShell to make changes to the computer. In reality, Windows PowerShell is not making changes to the computer - not yet. But using Windows PowerShell you can certainly make changes to the computer - if you have the rights, and this is what the dialog is prompting you for.

NOTE: It is possible to avoid this prompt by turning off User Account Control (UAC). However, UAC is a significant security feature, and therefore I do not recommend disabling UAC. We have fine-tuned it in Windows 7 and continuing through Windows 8.1 and greatly reduced the number of UAC prompts (from the number that used to exist in the introduction of UAC on Windows Vista. This is not "your grandma's UAC".)

Now that you are running Windows PowerShell with admin rights, you can do anything your account has permission to do. Therefore, if you were to, for example, run the Get-Disk cmdlets, you would see information similar to the following appear. "PS C:> get-disk

Number Friendly Name OperationalS Total Size Partition tatus Style

0 INTEL SSDSA2BW160G3L Online 149.05 GB MBR ""

Windows PowerShell Basics - Using PowerShell cmdlets

PowerShell cmdlets all work in a similar fashion. This simplifies their use. All Windows PowerShell cmdlets have a two-part name. The first part is a verb (not always strictly a grammatical verb however). The *verb* indicates the action for the command to take. Examples of verbs include Get, Set, Add, Remove, or Format. The *noun* is the thing to which the action will apply. Examples of nouns include Process, Service, Disk, or NetAdapter. A dash combines the verb with the noun to complete the Windows PowerShell command. Windows PowerShell commands, named cmdlets (pronounced command let), because they behave like small commands or programs are used standalone, or pieced together via a mechanism called the *pipeline* (refer to chapter two for the use of the *pipeline*).

The most common verb - Get

Out of nearly 2,000 cmdlets (and functions) on Windows 8, over 25 percent of them use the verb *Get*. The verb *Get* retrieves information. The Noun portion of the cmdlet specifies the information retrieved. To obtain information about the processes on your system, open the Windows PowerShell console by either clicking on the Windows PowerShell icon on the task bar (or typing PowerShell on the start screen of Windows 8 to bring up the search results for Windows PowerShell (as illustrated earlier)). Once the Windows PowerShell console appears, run the Get-Process cmdlet. To do this, use the Windows PowerShell Tab Completion feature to complete the cmdlet name. One the cmdlet name appears, press the <ENTER> key to cause the command to execute.

NOTE: The Windows PowerShell Tab Completion feature is a great time saver. It not only saves time (by reducing the need for typing) but it also helps to ensure accuracy, because Tab Completion accurately resolves cmdlet names - it is sort of like a spell checker for cmdlet names. For example, attempting to type a cmdlet name such as Get-NetAdapterEncapsulatedPacketTaskOffload accurately (for me anyway) could be an exercise in frustration. But using tab completion, I only have to type Get-Net and I hit the <TAB> key about six times and the correctly spelled cmdlet name appears in the Windows PowerShell console. Learning how to quickly, and efficiently use the tab completion is one of the keys to success in using Windows PowerShell.

Finding process information

To use the Windows PowerShell Tab Completion feature to enter the Get-Process cmdlet name onto the Windows PowerShell console command line, type the following on the first line of the Windows PowerShell console: Get-Pro + <tab> + <ENTER> The Get-Process command and the associated output from the cmdlet appear in the figure that follows.

2				Powe	erShell 3		_	х
PS C:\>	Get-Proce	255						^
Handles	NPM(K)	PM(K)	WS(K)	VM(M)	CPU(s)	Id	ProcessName	
99 84 35 33 52 375 364 114 179 335 293 1847 31 96 323 268 70 0 125 461 272 306 210 881 131 471 106	10 9 6 5 8 14 23 9 15 33 22 125 8 9 29 23 8 0 12 39 33 27 17 26 12 85 10	1676 1532 912 748 1788 1764 2064 1424 4704 33712 5756 76296 1160 1552 35708 21820 1072 0 2036 13564 29256 17700 9828 4336 1980 77616 2652	4868 4312 2908 2364 5832 3288 46212 4476 7400 44428 12804 131640 3504 40748 25208 3160 20 6516 12244 32636 23968 14112 9500 6696 54784 5904	62 46 48 26 54 48 90 54 69 277 101 861 48 250 244 30 0 86 791 568 170 153 38 79 248	0.00 0.27 59.98 0.83 0.03 0.14 0.02 0.47 0.08 0.00	2504 1180 1832 4944 628 732 2300 4240 1096 2340 4156 4188 3024 5636 980 4180 4584 3032 4804 4912 824 3388 2876	BtwRSupportService CamMute conhost conhost conhost csrss csrss CxAudMsg64 daemonu dwm EvtEng explorer fmapp hkcmd IAStorDataMgrSvc IAStorIcon ibmpmsvc Idle igfxpers LiveComm LnvHotSpotSvc loctaskmgr lpdagent lsass MobileHotspotclient MsMpEng nvSCPAPISvr	,

image007.png

To find information about Windows services, use the verb **Get** and the **noun** service. To type the cmdlet name, type the following: Get-Servi + <TAB> + <ENTER> **NOTE**: It is a Windows PowerShell convention to use singular nouns. While not universally applied (my computer has around 50 plural nouns) it is a good place to start. So if you are not sure if a noun (or parameter) is singular or plural, choose the singular - most of the time you will be correct.

Identifying installed Windows Hotfixes

To find a listing of Windows Hotfixes applied to the current Windows installation, use the Get-Hotfix cmdlet (the **verb** is Get and the **noun** is Hotfix). Inside the Windows PowerShell console, type the following: Get-Hotf + <TAB> + <ENTER> The command, and the output associated with the command appear here.




image009.png

Get detailed service information

To find information about services on the system, use the Get-Service cmdlet. Once again, it is not necessary to type the entire command. The following command uses Tab Expansion to complete the Get-Service command and to execute it. Get-Service + <TAB> + <ENTER> NOTE: The efficiency of Tab Expansion depends upon the number of cmdlets, functions, or modules installed on the computer. As more commands become available, the efficiency of Tab Expansion reduces correspondingly.

The following (truncated) output appears following the Get-Service cmdlet. "' PS C:> Get-Service

Status Name DisplayName

Running AdobeActiveFile... Adobe Active File Monitor V6

Stopped AeLookupSvc Application Experience

Stopped ALG Application Layer Gateway Service

Stopped AllUserInstallA... Windows All-User Install Agent

<TRUNCATED OUTPUT> "" ### Identifying installed network adapters

To find information about network adapters on your Windows 8 (or Windows Server 2012) machine, use the Get-NetAdapter cmdlet. Using Tab Expansion, type the following: Get-NetA + <TAB> + <ENTER> The command and associated output appear here. "' PS C:> Get-NetAdapter

Name InterfaceDescription ifIndex Status

__ ____ ___

Network Bridge Microsoft Network Adapter Multiplexo... 29 Up

Ethernet Intel(R) 82579LM Gigabit Network Con... 13 Not Pre...

vEthernet (WirelessSwi... Hyper-V Virtual Ethernet Adapter #4 31 Up

vEthernet (External Sw... Hyper-V Virtual Ethernet Adapter #3 23 Not Pre...

vEthernet (InternalSwi... Hyper-V Virtual Ethernet Adapter #2 19 Up

Bluetooth Network Conn... Bluetooth Device (Personal Area Netw... 15 Disconn...

Wi-Fi Intel(R) Centrino(R) Ultimate-N 6300... 12 Up "' ### Retrieving detected network connection profiles

If you want to see the network connection profile that Windows 8 (or Windows Server 2012) detected for each interface, use the Get-NetConnectionProfile cmdlet. To run this command, use the following command with Tab Expansion. Get-NetC + <TAB> + <ENTER> The command and associated output appear here. "' PS C:> Get-NetConnectionProfile

Name: Unidentified network

InterfaceAlias: vEthernet (InternalSwitch)

InterfaceIndex: 19

NetworkCategory : Public IPv4Connectivity : NoTraffic IPv6Connectivity : NoTraffic

Name: Network 10

InterfaceAlias : vEthernet (WirelessSwitch)

InterfaceIndex: 31

NetworkCategory : Public IPv4Connectivity : Internet

IPv6Connectivity: NoTraffic "'NOTE: Windows PowerShell is not case sensitive. There are a few instances where case sensitivity is an issue (for example when using Regular Expressions) but cmdlet names, parameters and values are not case sensitive. Windows PowerShell convention uses a combination of upper case and lower case letters (generally at syllable breaks in long noun names such as NetConnectionProfile) but this is not a requirement for Windows PowerShell to interpret accurately the command. This combination of upper case and lowercase letters are for readability. If you use Tab Expansion, Windows PowerShell automatically converts the commands to this fashion.

Getting the current culture settings

There are two types of culture settings on a typical Windows computer. There are the culture settings for the current culture settings. This includes information about the keyboard layout, and the display format of items such as numbers, currency, and dates. To find the value of these cultural settings, use the Get-Culture cmdlet. To call the Get-Culture cmdlet using Tab Expansion to complete the command, type the following on the current line of the Windows PowerShell console: Get-Cu + <TAB> + <ENTER> When the command runs basic information such as the Language Code ID number (LCID), the name of the culture settings, as well as the display name of the culture settings return to the Windows PowerShell console. The command and associated output appears here. "' PS C:> Get-Culture

LCID Name DisplayName

__ ___

1033 en-US English (United States) The second culture related grouping of information is the current user interface (UI) settings for Windows. The UI culture settings determine which text strings appear in user interface elements such as menus and error messages. To determine the current UI culture settings that are active use the Get-UICulture cmdlet. Using Tab Expansion to call the Get-UICulture cmdlet, type the following: Get-Ui+<TAB>+<ENTER>

The command and output associated from the command appears here. PS C:> Get-UICulture

LCID Name DisplayName

1033 en-US English (United States) ""

NOTE: On my laptop, both the current culture and the current UI culture are the same. This is not always the case, and at times, I have seen machines become rather confused when the user interface is set for a localized language, and yet the computer itself was still set for US English (this is especially problematic when using virtual machines created in other countries. In these cases, even a simple task like typing in a password becomes very frustrating. To fix these types of situations you can use the Set-Culture cmdlet.

Finding the current date and time

To find the current date or time on the local computer, use the Get-Date cmdlet. When typing the Get-Date cmdlet name in the Windows PowerShell console tab expansion does not help too much. This is because there are 15 cmdlets (on my laptop) that have a cmdlet name that begins with the letters Get-Da (this includes all of the Direct Access cmdlets as well as the Remote Access cmdlets). Therefore using Tab Expansion (on my laptop anyway) to get the date requires me to type the following: Get-Dat + <TAB> + <Enter> The above command syntax is just the same number of letters to type as doing the following: Get-Date + <ENTER> The following illustrates the command and the output associated with the command. PS C:\> Get-Date

Tuesday, November 20, 2012 9:54:21 AM

Generating a random number

Windows 2.0 introduced the Get-Random cmdlet, and when I saw it I was not too impressed. The reason was that I already knew how to generate a random number. Using the .NET Framework System.Random class, all I needed to do was create a new instance of the System.Random object, and call the _next _method. This appears here. PS C:\> (New-Object system.random).next() 225513766 Needless to say, I did not create all that many random numbers. I mean, who wants to do all that typing. But once I had the Get-Random cmdlet, I actually began using random numbers for all sorts of things. Some of the things I have used the Get-Random cmdlet to do appear in the following list.

- Pick prize winners for the Scripting Games
- Pick prize winners for Windows PowerShell user group meetings
- To connect to remote servers in a random fashion for load balancing purposes
- To create random folder names
- To create temporary users in active directory with random names
- To wait a random amount of time prior to starting or stopping processes and services (great for performance testing)

The Get-Random cmdlet has turned out to be one of the more useful cmdlets. To generate a random number in the Windows PowerShell console using Tab Expansion type the following on the first line in the console: Get-R +<TAB>+<ENTER> The command, and output associated with the command appears here. PS C:\> Get-Random 248797593

Windows PowerShell Basics - Supplying options for cmdlets

The easiest Windows PowerShell cmdlets to use require no options. But unfortunately, that is only a fraction of the total number of cmdlets (and functions) available in Windows PowerShell 4.0 as it exists on either Windows 8.1 or Windows Server 2012 R2. Fortunately, the same Tab Expansion technique used to create the cmdlet names on the Windows PowerShell console, works with **parameters** as well.

Using single parameters

When working with Windows PowerShell cmdlets, often the cmdlet only requires a single parameter to filter out the results. If a parameter is the default parameter, you do not have to specify the parameter name - you can use the parameter positionally. This means that the first value appearing after the cmdlet name, is assumed to be a value for the default (or position 1) parameter. On the other hand, if a parameter is a **named parameter** the parameter name (or parameter alias or partial parameter name) is always required when using the parameter.

Finding specific types of hotfixes

For example to find all of the _update _hotfixes, use the Get-HotFix cmdlet with the -Description parameter and supply a value of _update _to the -Description parameter. This is actually easier than it sounds. Once you type Get-Hot and press the <TAB> key you have the Get-Hotfix portion of the command. Then a space and -D <TAB> completes the Get-HotFix -Description portion of the command. Now you need to type Update and press <ENTER>. With a little practice, using Tab Expansion becomes second nature. You only need to type the following: Get-Hot + <TAB> + -D + <TAB> + Update + <ENTER> The completed command and the output associated with the command appear in the figure that follows.

		_ 🗆 🗙			
PS C:\> Get	:-HotFix -Descript	ion update			^
Source	Description	HotFi×ID	InstalledBy	InstalledOn	
EDLT EDLT EDLT EDLT EDLT EDLT EDLT EDLT	Update	KB2712101 KB2693643 KB2751352 KB2756872 KB2758994 KB2761094 KB2764870 KB2768703 KB2769034 KB2770041 KB2770407 KB976002	NT AUTHORITY\SYSTEM IAMMRED\ed NT AUTHORITY\SYSTEM	10/9/2012 12:00 10/22/2012 12:00 9/23/2012 12:00 10/9/2012 12:00 10/9/2012 12:00 10/9/2012 12:00 10/9/2012 12:00 10/12/2012 12:00 11/17/2012 12:0 11/17/2012 12:00 11/17/2012 12:00 11/17/2012 12:00 11/17/2012 12:00	
PS C:\> _					~

image011.png

Gets only hotfixes with the specified hotfix IDs. The default is all hotfixes on the computer.

```
1 Required? false
2 Position? 1
3 Default value All hotfixes
4 Accept pipeline input? false
5 Accept wildcard characters? False
```

```
Well, what about using the -Description parameter, you may ask? The help file tells \
that the -Description parameter is a named parameter. This means you can only use th\
e -Description parameter if you specify the parameter name as was accomplished earli\
er in this section. Here is the applicable portion of the help file for the -Descrip\
tion parameter.
```

-Description <String[]>

Gets only hotfixes with the specified descriptions. Wildcards are permitted. The default is all hotfixes on the computer.

```
1 Required? false
2 Position? named
```

Default value All hotfixes
 Accept pipeline input? false
 Accept wildcard characters? True

Finding specific processes

1

To find process information about a single process, I use the -Name parameter. Becau\
se the -Name parameter is the default (position 1) parameter for the Get-Process cmd\
let, you do not have to specify the -Name parameter when calling Get-Process if you \
do not wish to do so. For example, to find information about the PowerShell process \
by using the Get-Process cmdlet type the following command in the first line of the \
Windows PowerShell console by using Tab Expansion:

 $Get-Pro + < TAB > + < SPACE > + Po + < TAB > + < ENTER > \ \$ The completed command and associated output appears here. PS C:> Get-Process powershell

Handles NPM(K) PM(K) WS(K) VM(M) CPU(s) Id ProcessName

 $607\ 39\ 144552\ 164652\ 718\ 5.58\ 4860\ powershell$ You can tell that the Get-Process cmdlet accepts the -Name parameter in a positional manner because the Help file states it is in position 1. This appears here. -Name <String[]> Specifies one or more processes by process name. You can type multiple

Specifies one or more processes by process name. You can type multiple process names (separated by commas) and use wildcard characters. The parameter name ("Name") is optional.

```
1 Required? false
2 Position? 1
```

- 3 Default value
- 4 Accept pipeline input? true (ByPropertyName)
- 5 Accept wildcard characters? True

NOTE: Be careful using positional parameters. This is because they can be conful sing. For example, the first parameter for the Get-Process cmdlet is the -Name parameter, but the first position parameter for the Stop-Parameter is the -ID parameter. As a best practice always refer to the Help files to see what the parameters actually y are called, and the position in which they are expected. This is even more important when using cmdlet with multiple parameters - such as the Get-Random cmdlet discussed next.

8

Generating random numbers in a range

10

13 14

15

When used without any parameters, the Get-Random cmdlet returns a number that is in $\$ the range of 0 to 2,147,483,647. We have never had a Windows PowerShell user group m\ eeting in which there were either 0 people in attendance, nor have we had a Windows $\$ PowerShell user group meeting with 2,147,483,647 people in attendance. Therefore whe\ n handing out prizes at the end of the day, it is important to set a different minim\ um and maximum number.

16 17 18

19

NOTE: When using the -Maximum parameter for the Get-Random cmdlet keep in mind \ that the maximum number never appears. Therefore, if you have 15 people attending yo\ ur Windows PowerShell user group meeting, you would want to set the -Maximum paramet\ er to 16 (unless you do not like the 15 person and do not want them to win any prize\ s).

222324

25

2627

28

The default parameter for the Get-Random cmdlet is the -Maximum parameter. This mean\
s that you can use the Get-Random cmdlet to generate a random number in the range of\
0 to 20 by using Tab Expansion on the first line of the Windows PowerShell console.\
Type the following (remember Get-Random never reaches the maximum number, therefore\
always use a number 1 greater than the desired upper number):

Get-R + <TAB> + <SPACE> + 21 If you want to generate a random number between 1 and 20, you might think you could use Get-Random 1 21, but that generates an error. The command and the error appear here. PS C:> Get-Random 1 21

Get-Random : A positional parameter cannot be found that accepts argument '21'.

At line:1 char:1

+ Get-Random 1 21

 $+ \sim \sim \sim$

- + CategoryInfo : InvalidArgument: (:) [Get-Random], ParameterBindingEx ception
- + FullyQualifiedErrorId: PositionalParameterNotFound,Microsoft.PowerShell.Comm ands.GetRandomCommand "' The error states that *a positional parameter cannot be found that accepts argument '21'*. This is because the Get-Random only has one positional parameter the Maximum parameter. The -Minimum parameter is a named parameter (this appears in the Help file for the Get-Random cmdlet. Use of the Help files appears in Chapter two).

To generate a random number in the range of 1 to 20, use named parameters. To assist in creating the command use Tab Expansion for the cmdlet name as well as for the parameter names. Type the following to create the command using Tab Expansion. Get-R + $\langle TAB \rangle$ + $\langle T$

One of the things that quickly becomes confusing with Windows PowerShell cmdlets is that there are often different ways of using the same cmdlet. For example, you can specify the -Minimum and the -Maximum parameters, but you cannot also specify the -Count parameter. This is a bit unfortunate, because it would seem that using the -Minimum and the -Maximum parameters to specify the minimum and the maximum numbers for the random numbers makes sense. When the Windows PowerShell user group has five prizes to give away it is inefficient to have to either write a script to generate the five random numbers. It is also inefficient to have to run the same command five times.

This is where command sets come into play. The -Minimum and the -Maximum parameters specify the range within which to pick a single random number. To generate more than one random number use the -Count parameter. Here are the two parameter sets. "' Get-Random [[-Maximum] <Object>] [-Minimum <Object>] [-SetSeed <Int32>] [<CommonParameters>]

Get-Random [-InputObject] <Object[]> [-Count <Int32>] [-SetSeed <Int32>]

[<CommonParameters>] "The first parameter set accepts -Maximum, -Minimum and -SetSeed. The second parameter set accepts -InputObject, -Count and -SetSeed. Therefore you cannot use -Count with -Minimum or -Maximum - they are in two different groups of parameters (called parameter sets).

NOTE: It is quite common for Windows PowerShell cmdlets to have multiple parameter sets. Tab Expansion only offers parameters from one parameter set - therefore when you choose a parameter (such as -Count from Get-Random) the non-compatable parameters do not appear in tab Expansion. This feature keeps you from creating invalid commands. For an overview of a cmdlets parameter sets, use the Get-Help cmdlet.

Generating a certain number of random numbers

The Get-Random cmdlet, when used with the -Count parameter accepts an -InputObject parameter. The -InputObject parameter is quite powerful. The help file, appearing here, states that it accepts a collection of objects. "' -InputObject <Object[]>

Specifies a collection of objects. Get-Random gets randomly selected objects in random order from the collection. Enter the objects, a variabl that contains the objects, or a command or expression that gets the objects. You can also pipe a collection of objects to Get-Random.

Required? true Position? 1

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? False An array (or a range) of numbers just happens to also be a collection of objects. The easiest way to generate a range (or an array) of numbers is to use the range operator. The **range operator** is two dots (periods) between two numbers. The **range operator** does not require spaces between the numbers, and dots. This appears here. PS C > 1..5

1 2 3

5 Now to pick five random numbers from the range of 1 to 10, only requires the command appearing here. (The parentheses are required around the range of 1 to 10 numbers to ensure the range of numbers creates prior to attempting to select five from the collection. Get-Random -InputObject (1..10) -Count 5 The command and output associated with the command appear here. PS C:> Get-Random -InputObject (1..10) -Count 5

Windows PowerShell Basics - Using command line utilities

As easy as Windows PowerShell is to use, there are times when it is easier to find information by using a command line utility. For example, to find IP configuration information you only need to use the _Ipconfig.exe _utility. You can type this directly into the Windows PowerShell console and read the output in the Windows PowerShell console. This command and associated output appears here in truncated form. "' PS C:> ipconfig

Windows IP Configuration

. . . . : 192.168.3.100

Wireless LAN adapter Local Area Connection* 14:

Media State : Media disconnected Connection-specific DNS Suffix . :

Ethernet adapter vEthernet (WirelessSwitch):

Connection-specific DNS Suffix . : quadriga.com Link-local IPv6 Address : fe80::915e:d324:aa0f:a54b%31 IPv4 Address : 192.168.13.220 Subnet Mask : 255.255.248.0 Default Gateway : 192.168.15.254

Wireless LAN adapter Local Area Connection* 12:

Media State : Media disconnected Connection-specific DNS Suffix . :

Ethernet adapter vEthernet (InternalSwitch):

Connection-specific DNS Suffix . : Link-local IPv6 Address : fe80::bd2d:5283:5572:5e77%19 IPv4 Address : 192.168.3.228 Subnet Mask : 255.255.255.0 Default Gateway

<OUTPUT TRUNCATED> "' To obtain the same information using Windows PowerShell would require a more complex command. The command to obtain IP information is Get-NetIPAddress, But there are several advantages. For one thing, the output from the _IpConfig.exe _command is text, whereas the output from Windows PowerShell is an object. This means you can group, sort, filter, and format the output in an easy fashion.

The cool thing is that with Windows PowerShell console, you have not only the simplicity of the command prompt, but you also have the powerful Windows PowerShell language built in. Therefore, if you need to refresh Group Policy three times and wait for five minutes between refreshes, you can use the command appearing here (looping is covered in chapter eleven). 1..3 | % {gpupdate ; sleep 300}

Windows PowerShell Basics - Working with help options

The first thing you need to do is to update the help files on your system. This is because Windows PowerShell 3.0 introduces a new model in which the help files update on a regular basis.

To update help on your system, you must ensure two things. The first is that you open the Windows PowerShell console with ADMIN rights. This is because the Windows PowerShell help files reside in the protected WindowsSystem32WindowsPowerShell directory. Once you have launched the Windows PowerShell console with admin rights you need to ensure your computer has Internet access so it can download and install the updated files. If your computer does not have Internet connectivity, it will take several minutes before the command times out (Windows PowerShell tries really hard to obtain the updated files). If you run the Update-Help cmdlet with no parameters Windows PowerShell attempts to download updated help for all modules stored in the default Windows PowerShell modules locations that support updatable help. To run Update-Help more than once a day use the -Force parameter as appears here. Update-Help -Force Even without downloading updated Windows PowerShell help, the help subsystem displays the syntax of the cmdlet and other rudimentary information about the cmdlet. In this way.

To display help information from the internet, use the -Online switch. When used in this way, Windows PowerShell causes the default browser to open to the appropriate page from the Microsoft TechNet web site.

In the enterprise, network administrators may want to use the Save-Help cmdlet to download help from the Internet. Once downloaded, the Update-Help cmdlet can point to the network share for the files. This is an easy task to automate, and can run as a scheduled task.

Windows PowerShell Basics - Working with modules

What makes the big difference in capabilities between Windows PowerShell 4.0 installed on Windows 7 or Windows 8.1 is not the difference in the capability of Windows PowerShell 4.0. The package provides the same abilities. The difference is the modules introduced with Windows 8 and expanded in Windows 8.1. To find out the commands that a module provides, I use the Get-Command cmdlet and specify the name of a particular module. In this example, I look at the commands provided by the NetAdapter. Get-Command-ModuleNetAdapter If I use the Get-Command cmdlet and an error arises, it may be because the module has not yet loaded. To load the module use the Import-Module cmdlet. This command appears here. Import-ModuleNetAdapter If I am curious as to the number of commands exposed by the module, I can pipeline the results to the Measure-Object cmdlet. This command appears here. Get-Command-Modulenetadapter | Measure-Object

Working with Network adapters

Windows offers many different ways to work with Network Adapters. The correct choice depends upon several things. First probably, I need to know what version of the operating system I am running. In most cases the version of the operating system will either limit or expand my options for working with Network Adapters. Next I need to know if I am working locally or remotely, because where I run my commands from often determine my choice of tool. Lastly I always choose the tool that is easiest for me to do the job I have to perform. This is not always the easiest tool for anyone to use, but I choose the tool that I know. For me, for example, typing even a dozen commands into the Windows PowerShell ISE is much easier than attempting to use NetSh in some context with which I am unfamiliar. In addition, by typing my commands into the Windows PowerShell ISE, I can easily save my commands off as a Windows PowerShell script, that I can reuse. Of course I can reuse NetSh commands - I do all the time, but it is an extra step. So, to summarize, what is my decision matrix (assuming identical capabilities)?

- 1. Version of Operating System
- 2. Remoting capability
- 3. Ease of use

All things being equal, what tools are available to me to use to accomplish my work with network adapters?

- 1. Windows PowerShell
- 2. NetSH
- 3. Windows Management Instrumentation (WMI)
- 4. VBScript
- 5. Console Utilities

In this booklet, I will talk about each of these approaches as I look at the different tasks. So what tasks am I talking about? Well, I am specifically talking about the network adapter. So here are the things I am going to cover:

- 1. Identifying network adapters
- 2. Enabling and disabling network adapters
- 3. Renaming network adapters
- 4. Finding connected network adapters
- 5. Identifying network adapter power setting
- 6. Configuring network adapter power settings

7. Gathering network adapter statistics

Along the way, I will be showing some pretty cool Windows PowerShell tricks.

PowerTip: Find protocol binding on net adapters using PowerShell

Question: How can you use Windows PowerShell to show which enabled protocols are bound to your network adapters using Windows 8.1 and PowerShell 4.0?

Answer: Use the Get-Netadapter cmdlet to retrieve all of the network adapters on your system. Then pipeline it to the Get-NetAdapterBinding cmdlet and filter on enabled is equal to true. This command appears here: Get-NetAdapter|Get-NetAdapterBinding|-enabled-eq\$true

Identifying network adapters

One of the great things about Windows Management Instrumentation (WMI) is the way that it can provide detailed information. The bad thing is that it requires a specialist level of knowledge and understanding to effectively use and to understand the information (either that or a good search engine, such as BING⁵ and an awesome repository of information such as the Script Center⁶).

Using raw WMI to identify network adapters

One of the cool things about Windows PowerShell, since version 1.0, is that it provides easier access to WMI information. The bad thing, of course, is that it is still wrestling with WMI, which some IT Pro's seem to hate (or at least dislike). The great thing about using raw WMI is compatibility with older versions of the operating system. For example, using raw WMI and Windows PowerShell would make it possible to talk to Windows XP, Windows 2003 Server, Windows 2008 Server, Vista, Windows Server 2008 R2 and Windows 7, in addition to the modern operating systems of Windows 8, 8.1 and Windows Server 2012 and Windows Server 2012 R2.

So how do I do it? I used to be able to find our real network card by finding the one that was bound to TCP/IP. I would query the Win32_NetworkAdapterConfiguration WMI class, and filter on the IPEnabled property. Using this approach, I would have done something like this: Get-WmiObject-ClassWin32_NetworkAdapterConfiguration -filter"IPEnabled = \$true" The problem with this methodology nowadays is that some of the pseudo adapters are also IPEnabled. The above command would eliminate many, but not necessarily all of the adapters.

A better approach is to look at the Win32_NetworkAdapter class and query the NetConnectionStatus property. Using this technique, I return only network adapter devices that are actually connected to a network. While it is possible that a pseudo adapter could sneak under the wire, the likelihood is more remote. In this command, I will use the Get-WmiObject PowerShell cmdlet to return all instances of Win32_NetworkAdapter class on the computer. I then create a table to display the data returned by the NetConnectionStatus property. Get-WmiObject-ClassWin32_NetworkAdapter| Format-Table-PropertyName, NetConnectionStatus-AutoSize The fruit of our labor is somewhat impressive. I have a nice table that details all of the fake and real network adapters on our laptop, as well as the connection status of each. Here is the list from my laptop. "Name NetConnectionStatus

⁵http://www.bing.com/

⁶http://technet.microsoft.com/en-us/scriptcenter

WAN Miniport (L2TP) WAN Miniport (PPTP) WAN Miniport (PPPOE) WAN Miniport (IPv6) Intel(R) PRO/1000 PL Network Connection 2 Intel(R) PRO/Wireless 3945ABG Network Connection 0 WAN Miniport (IP) Microsoft 6to4 Adapter Bluetooth Personal Area Network RAS Async Adapter isatap.{51AAF9FF-857A-4460-9F17-92F7626DC420} Virtual Machine Network Services Driver Microsoft ISATAP Adapter Bluetooth Device (Personal Area Network) 7 6TO4 Adapter Microsoft 6to4 Adapter Microsoft Windows Mobile Remote Adapter isatap.launchmodem.com isatap.{647A0048-DF48-4E4D-B07B-2AE0995B269F} Microsoft Windows Mobile Remote Adapter Microsoft 6to4 Adapter Microsoft Windows Mobile Remote Adapter 6TO4 Adapter Microsoft 6to4 Adapter Microsoft Windows Mobile Remote Adapter isatap.{C210F3A1-6EAC-4308-9311-69EADBA00A04} isatap.launchmodem.com Virtual Machine Network Services Driver Virtual Machine Network Services Driver Teredo Tunneling Pseudo-Interface isatap.{647A0048-DF48-4E4D-B07B-2AE0995B269F} "There are two things you will no doubt notice. The first is that most of the network adapters report no status what-so-ever. The second thing you will notice is that the ones that do report a status do so in some kind of code. The previous table is therefore pretty much useless! But it does look nice.

A little work in the Windows SDK looking up the Win32_NetworkAdapter WMI class and I run across the following information: "' Value Meaning

- 0 Disconnected
- 1 Connecting
- 2 Connected
- 3 Disconnecting
- 4 Hardware not present
- 5 Hardware disabled
- 6 Hardware malfunction
- 7 Media disconnected
- 8 Authenticating
- 9 Authentication succeeded
- 10 Authentication failed
- 11 Invalid address
- 12 Credentials required The value of 2 means the network adapter is connected. Here is the code I wrote to exploit the results of our research. Get-WmiObject -classwin32_networkadapter -filter "NetConnectionStatus = 2" | Format-List -Property [a-z]* " Such ecstasy is short lived; however, when I realize that while I have indeed returned information about a network adapter that is connected, I do not have any of the configuration information from the card.

What I need is to be able to use the NetConnectionStatus property from Win32_Networkadapter and to be able to obtain the Tcp/Ip configuration information from the Win32_NetworkAdapterConfiguration WMI class. This sounds like a job for an association class. In VBScript querying an Association

class involved performing confusing AssociatorsOf queries (Refer to the MSPress book, "Window Scripting with WMI: Self Paced Learning Guide" for more information about this technique.)

Using the association class with Windows PowerShell, I come up with the FilterAssociatedNetworkAdapters.ps1 script shown here.

FilterAssociatedNetworkAdapters.ps1 "' Param(\$computer="localhost")

Write-Host-ForegroundColorcyan"Network adapter settings on \$computer"

Get-WmiObject -Class win32_NetworkAdapterSetting '-computername \$computer| Foreach-object ' $\{If(([wmi]\$_.element).netconnectionstatus -eq 2) \{funline("Adapter: \$(\$_.setting)") [wmi]\$_.setting [wmi]\$_.element \} #end if } #end foreach I begin the script by using a command line parameter to allow us to run the script remotely if needed. I use the Param statement to do this. I also create a function named funline that is used to underline the results of the query. It makes the output nicer if there is a large amount of data returned. Param($computer="localhost")$

functionfunline (\$strIN) { \$num=\$strIN.length for(\$i=1; \$i-le\$num; \$i++) { \$funline=\$funline+"=" } Write-Host-ForegroundColoryellow\$strIN Write-Host-ForegroundColordarkYellow\$funline } #end funline I print out the name of the computer by using the Write-Host cmdlet as seen here. I use the color cyan so the text will show up real nice on the screen (unless of course your background is also cyan, then the output will be written in invisible ink. That might be cool as well.) Write-Host-Foreground Colorcyan "Network adapter settings on \$computer" Then I get down to actual WMI query. To do this, I use the Get-WmiObject cmdlet. I use the -computername parameter to allow the script to run against other computers, and I pipeline the results to the ForEach-Object cmdlet. Get-WmiObject -Class win32_NetworkAdapterSetting '-computername \$computer| Foreach-object ' The hard part of the query is seen here. I need a way to look at the netConnectionStatus property of the Win32_NetworkAdapter class. This class is referred to by the reference returned from the association query. It is called element. To gain access to this class, I use the reference that was returned and feed it to the [WMI] type accelerator (it likes to receive a path, and this is what the reference is). Since the reference refers to a specific instance of a WMI class, and since the [WMI] type accelerator can query a specific instance of a class, I are now able to obtain the value of the netConenctionStatus property. So I say in our script, if it is equal to 2, then I will print out the name of the network adapter, and the configuration that is held in the setting property and the adapter information that held in the element property. This section of the code is seen here. { If(([wmi]\$.element).netconnectionstatus -eq2) { funline("Adapter: \$(\$.setting)") [wmi]\$.setting [wmi]\$_.element } #end if "' The result of running the script is that it displays information from

 $^{^{7}}http://www.amazon.com/Microsoft\%C2\%AE-Windows\%C2\%AE-Scripting-WMI-Self-Paced/dp/0735622310/ref=sr_1_1?ie=UTF8\&qid=1389289441\&sr=8-1\&keywords=ed+wilson+wmi$

both the Win32_NetworkAdapter WMI class and the Win32_NetworkAdapterConfiguration class. It also shows us I only have one connected network adapter.

Using NetSh

Microsoft created NetSh back in 2000, and it has been a staple of networking ever since then. When I open it up, now days, it displays a message saying that it might be removed in future versions of Windows, and therefore I should begin using Windows PowerShell. Here is the message:




image013.png

Now, because NetSh is an old style menu type application, it is possible to enter NetSh, and walk my way down through the menus until you arrive at the proper location. Along the way, if I get lost, I can use the? to obtain help. The problem, is that the help is quite often not very helpful, and therefore it takes me at times nearly a dozen times before the command is correct. The great thing is that, for the most part, Once I figure out a command, I can actually keep track of my location in the program, and back all the way out and enter the command as a one linner. Here is the NetSh command to display network interface information that is bound to Ipv4: netsh interface ipv4 show interfaces. The output appears here:




image015.png

Using PowerShell on Windows 8 or above

If I have the advantage of Windows 8 or 8.1 or Windows Server 2012 or Windows Server 2012 R2, then I have the built in NetAdapter module. Due to the way that modules autoload on Windows Powell I do not need to remember that I am using functions that exist in the NetAdapter module. I can use either Windows PowerShell 3 or Windows PowerShell 4 and the behavior will be the same (Windows 8.1 and Windows Server 2012 R2 come with Windows PowerShell 4 and Windows 8 and Windows Server 2012 come with Windows PowerShell 3).

The Get-NetAdapter cmdlet returns the name, interface description, index number, and status of all network adapters present on the system. This is the default display of information and appears in the figure that follows.

```
_ 🗆
                                          Windows PowerShell
PS C:\> Get-NetAdapter
                              InterfaceDescription
                                                                              ifIndex Status
Name
Ethernet
                              Intel(R) 82579LM Gigabit Network Con...
                                                                                     4 Up
vEthernet (internalSwi... Hyper-V Virtual Ethernet Adapter #4
                                                                                    19 Up
vEthernet (WiFiExterna... Hyper-V Virtual Ethernet Adapter #3
vEthernet (externalSwi... Hyper-V Virtual Ethernet Adapter #2
                                                                                    16 Not Pre.
                                                                                    12 Up
                              Intel(R) Centrino(R) Ultimate-N 6300...
                                                                                     3 Not Pre...
Bluetooth Network Conn... Bluetooth Device (Personal Area Netw...
                                                                                     7 Not Pre...
PS C:\> _
```

image017.png

To focus in on a particular network adapter, I use the _name _parameter and supply the name of the network adapter. The good thing, is that in Windows 8 (and on Windows Server 2012) the network connections receive new names. No more of the "local area connection" and "local area connection(2)

to attempt to demystify. The wired network adapter is simply _Ethernet _and the wireless network adapter is _Wi-Fi. _The following command retrieves only then _Ethernet _network adapter. Get-NetAdapter -Name Ethernet _To dive into the details of the _Ethernet _network adapter, I pipeline the returned object to the Format-List cmdlet and I choose all of the properties. The command appearing here uses the _fl _alias for the Format-List cmdlet. Get-NetAdapter -Name ethernet|Format-List * The command and output associated with the command appear in the figure that follows.




image019.png

There are a number of excellent properties that might bear further investigation, for example there are the _adminstatus _and the _mediaconnectionstatus _properties. The following command returns those two properties. Get-NetAdapter -Name ethernet |select adminstatus, MediaConnectionState Of course, there are other properties that might be interesting as well. These properties appear here, along with the associated output (the following is a single log-

ical command broken on two lines). Get-NetAdapter -Name ethernet | select ifname, adminstatus, MediaConnectionState, LinkSpeed, PhysicalMediaType The output from the above command appears here: ifName: Ethernet_7 AdminStatus: Down MediaConnectionState: Unknown LinkSpeed: 0 bps PhysicalMediaType: 802.3 I decide to look only for network adapters that are in the admin status of _up. _I use the command appearing here. "' PS C:> Get-NetAdapter|whereadminstatus-eq"up"

Name InterfaceDescription ifIndex Status — — — — vEthernet (InternalSwi... Hyper-V Virtual Ethernet Adapter #3 22 Up vEthernet (ExternalSwi... Hyper-V Virtual Ethernet Adapter #2 19 Up Bluetooth Network Conn... Bluetooth Device (Personal Area Netw... 15 Disconn... Wi-Fi Intel(R) Centrino(R) Ultimate-N 6300... 12 Up To find the disabled network adapters, I change the _adminstatus _from _up _to _down. _This command appears here. Get-NetAdapter|whereadminstatus-eq"down" I go back to my previous command, and modify it to return WI-FI information. This command, and associated output appears here (this is a single logical command). PS C:> Get-NetAdapter-Name wi-fi| select ifname,adminstatus,MediaConnectionState,LinkSpeed,PhysicalMediaType

ifName: WiFi_0 AdminStatus: Up MediaConnectionState: Connected LinkSpeed: 54 Mbps PhysicalMediaType: Native 802.11 If I want to find any network adapters sniffing the network, I look for _promiscousmode. _This command appears here. Get-NetAdapter | PromiscuousMode -eq \$true When I combine the Get-NetAdapter function with the Get-NetAdapterBinding function I can easily find out which protocols are bound to which network adapter. I just send the results to the Where-Object and check to see if the enabled property is equal to true or not. Here is the command. Get-NetAdapter | Get-NetAdapterBinding | ? enabled -eq \$true "Here is an example of both the command and the output from the command.




image021.png

If I want to find which network adapters have the Client for Microsoft Networks bound, I need to first see which protocols are enabled (using the syntax from the previous command) and I need to see which one of the enabled protocols have the display name of Client for Microsoft Networks. This requires a compound where-object statement and therefore I cannot use the simplified syntax. Also, because only one of the protocols begins with Client - I can use that to shorten my query just a bit. Here is the command I use (this is a one line command that I broke at the pipe character to make a better display). Get-NetAdapter | Get-NetAdapterBinding | where {\$_.enabled -AND\$_.displayname -match 'client'} The command and associated output appear in the figure here.




image023.png

Enabling and disabling network adapters

One of the most fundamental things that I do with a network adapter is either enable or disable it. In fact, I perform these tasks several times a week. This is because my primary work device is a laptop and it has built-in wireless network adapters. Not surprising, all modern laptops have both wired and wireless connections available. But when I am at home, in my office I want to have my laptop use the gigabit Ethernet switch that I have, and not go through the significantly slower wireless adapter. If I am on the road, I want to know if my wireless network adapter is enabled or not, and I want to control whether it connects to say a network named Starbucks for example. If I do not control such a thing, my laptop will automatically connect to every wireless it has ever seen before. This is why, for example , I wrote this blog article about cleaning out wireless network history. Chris Wu, a Microsoft PFE also wrote an article that takes a different approach. It is a good read as well.

PowerTip : Enable all network adapters

Question: You are troubleshooting your Windows 8.1 laptop and want to quickly enable all network adapters. How can you do this?

Answer: Use the Get-NetAdapter and the Enable-NetAdapter commands. The command line appears here: Get-NetAdapter | Where status -ne up | Enable-NetAdapter ## Using Devcon

Option Explicit

Dim objShell Dim objExec Dim onWireLess Dim onLoopBack Dim turnON Dim turnOFF Dim yesNO Dim message, msgTitle Dim strText

 $^{{}^{8}}http://blogs.technet.com/b/heyscriptingguy/archive/2013/06/16/weekend-scripter-use-powershell-to-manage-auto-connect-wireless-networks.aspx$

⁹http://blogs.technet.com/b/heyscriptingguy/archive/2012/06/10/weekend-scripter-use-powershell-to-manage-windows-network-locations.aspx

¹⁰http://support.microsoft.com/kb/311272

message = "Turn On Wireless? Loop is disabled" & vbcrlf & "if not, then wireless is disabled and loop enabled"

msgTitle = "change Network settings" onWireLess = "PCMCIADell-0156-0002" onLoopBack = "*loop" turnON = "enable" turnOFF = "disable" Const yes = 6 Set objShell = CreateObject("wscript.shell") yesNO = MsgBox(message,vbyesNO,msgTitle)

If yesNO = yes Then WScript.Echo "yes chosen" Set objExec = objShell.exec("cmd /c c:\devcon " & turnON & onWireLess) subOUT Set objExec = objShell.exec("cmd /c c:\devcon " & turnOFF & onLoopBack) subOUT Else WScript.Echo "no chosen" Set objExec = objShell.exec("cmd /c c:\devcon " & turnOFF & onWireLess) subOUT Set objExec = objShell.exec("cmd /c c:\devcon " & turnON & onLoopBack) subOUT End If

Sub subOUT Do until objExec.StdOut.AtEndOfStream strText = objExec.StdOut.ReadLine() Wscript.Echo strText Loop End sub "" ## Using WMI

Beginning with Windows Vista (and Windows Server 2008) the Win32_NetworkAdapter class gains two methods: disable and enable. These are documented on MSDN here¹¹. These methods are instance methods which means that to use them, I need to first obtain an instance of the WMI class. What does this mean? Well I am using Win32_NetworkAdapter and therefore I am working with network adapters. So, I need to get a specific network adapter, and then I can disable it or enable it. Here is how it might work: "" \$wmi=Get-WmiObject-ClassWin32_NetworkAdapter-filter"Name LIKE '%Wireless%'"

\$wmi.disable() OR \$wmi=Get-WmiObject-ClassWin32_NetworkAdapter-filter"Name LIKE '%Wireless%'"

\$wmi.enable() "" The thing to keep in mind is that when calling a method in Windows PowerShell, the parenthesis are required.

If I need to specify alternate credentials, I can specify a remote computer name and an account that has local admin rights on the remote box. The code would appear like the following: \$\mi=Get-\miObject-Class\min32_NetworkAdapter-filter\name LIKE '\mathbb{W}\mireless\mathbb{'}\nu-credential (Get-Credential) -computernameremotecomputer \$\min.disable()\) Keep in mind that WMI does not permit alternate credentials for a local connection. Attempts to use alternate credentials for a local connection results in the error appearing here: "PS C:> gwmi win32_networkadapter - Credential (Get-Credential)

cmdlet Get-Credential at command pipeline position 1

Supply values for the following parameters:

Credential

gwmi : User credentials cannot be used for local connections At line:1 char: + gwmi win32_- networkadapter -Credential (Get-Credential) + $\sim\sim$ + CategoryInfo : InvalidOperation: (:) [Get-WmiObject], ManagementException + FullyQualifiedErrorId : GetWMIManagementException,Microsoft.PowerShe


 $^{^{11}}http://msdn.microsoft.com/en-us/library/aa394216\%28v=vs.85\%29.aspx$

ds.GetWmiObjectCommand "" This error, for local connections, is not a Windows PowerShell thing, WMI has always behaved in this manner, even going back to the VBScript days.

Using the NetAdapter module

In Windows 8 (and above), I can use Windows PowerShell to stop or to start a network adapter by using one of the CIM commands. Of course, the function wraps the WMI class, but it also makes things really easy. The _netadapter _functions appear here (gcm is an alias for the Get-Command cmdlet) "" PS C:> gcm -Noun netadapter | select name, modulename

Name ModuleName — — —— Disable-NetAdapter NetAdapter Enable-NetAdapter NetAdapter Cet-NetAdapter NetAdapter Rename-NetAdapter NetAdapter Restart-NetAdapter NetAdapter Set-NetAdapter NetAdapter "" NOTE: To enable or to disable network adapters requires admin rights. Therefore you must start the Windows PowerShell console with an account that has rights to perform the task.



The various network adapters on my laptop appear in the figure that follows.

I do not like having enabled, disconnected network adapters. Instead, I prefer to only enable the network adapter I am using (there are a number of reasons for this such as simplified routing tables, performance issues, and security concerns). In the past, I wrote a script, now I only need to use a Windows PowerShell command. If I only want to disable the non-connected network adapters, the command is easy. It appears here. Get-NetAdapter | ? status-ne up | Disable-NetAdapter | The problem with the previous command is that it prompts. This is not much fun when there are multiple network adapters to disable. The prompt appears here.





image027.png

To suppress the prompt, I need to supply \$false to the -confirm parameter. This appears here. Get-NetAdapter | ? status-ne up | Disable-NetAdapter -Confirm: \$false A quick check in con-



trol panel shows the disconnected adapters are now disabled. This appears here.

If I want to enable a specific network adapter, I use the Enable-Network adapter. I can specify by name as appears here. Enable-NetAdapter -Name ethernet -Confirm:\false If I do not want to type the adapter name, I can use the Get-NetAdapter cmdlet to retrieve a specific network adapter and then enable it. This appears here. Get-NetAdapter -Name vethernet*| ? status -eq disabled| Enable-NetAdapter -Confirm:\false It is also possible to use wild card characters with the Get-NetAdapter to retrieve multiple adapters and pipeline them directly to the Disable-NetAdapter cmdlet. The following permits the confirmation prompts so that I can selectively enable or disable the adapter as I wish. "" PS C:> Get-NetAdapter -Name vethernet* | Disable-NetAdapter

Confirm

Are you sure you want to perform this action?

Disable-NetAdapter 'vEthernet (InternalSwitch)'

[Y] Yes [A] Yes to All [N] No [L] No to All [S] Suspend [?] Help (default is "Y"):y

Confirm

Are you sure you want to perform this action?

Disable-NetAdapter 'vEthernet (ExternalSwitch)'

[Y] Yes [A] Yes to All [N] No [L] No to All [S] Suspend [?] Help (default is "Y"):n ""

Renaming the network adapter

Depending on the version of your operating system, you will have different capabilities available for renaming the network adapter. These methods involve using Netsh, WMI, and the functions from the NetAdapter module.

PowerTip : Renaming the network adapter

Question: You want to rename you network adapter. How can you do this using Windows PowerShell on Windows 8 or above?

Answer: Use the Get-Netadapter function to retrieve the specific network adapter and pipeline the results to the Rename-NetAdapter function. This technique appears here: Get-NetAdapter -Name Ethernet|Rename-NetAdapter -NewName MyRenamedAdapter ## Using NetSh

To rename the network adapter using NetSh I need to know the interface name, and the new name I want to use. This is about it. To find the network adapter names, I can also use NetSh. Here is the command: netsh interface ipv4 show interfaces NetSh is available everywhere right now. So, I can use NetSh to configure network adapters from Windows 2000 forward - so it has the greatest amount of backward compatibility. But it is deprecated, and therefore may not always be available going forward. To rename a network interface using NetSh, I can use a command such as the one appearing here: NetSh interface set interface name="Ethernet" newname="RenamedAdapter" ## Using WMI

Beginning with Windows Vista, it is possible to use WMI to rename the network interface. The thing to keep in mind, is that the property that I change is NetConnectionID and not the name property. Because this command modified the NetConnectionID property, it is a simple property assignment, and not a method call. The Win32_NetworkAdapter WMI class is documented on MSDN¹² and the article shows the properties that are Read and Write. The steps to using WMI include the following:

- 1. Retrieve the specific instance of the network adapter
- 2. Assign a new value for the NetConnectionID property
- 3. Use the Put method to write the change back to WMI

The following code illustrates these three steps using a network adapter that is named Ethernet. The command will rename the network adapter named Ethernet to RenamedConnection: ""

\$wmi = Get-WmiObject -Class Win32_NetworkAdapter -Filter "NetConnectionID = 'Ethernet'"

\$wmi.NetConnectionID = 'RenamedConnection' \$wmi.Put()

"" The following figure shows using WMI to rename the network adapter.

 $^{^{12}} http://msdn.microsoft.com/en-us/library/aa394216\%28v=vs.85\%29.aspx$




image031.png

Using WMI on Windows 7 and above

On Windows 7 and Windows Server 2008 R2, it is not necessary to use the Get-WmiObject cmdlet, assign new values for the property and call the Put method. This is because the Set-CimInstance cmdlet permits accomplishing this feat as single command. The easiest way to use Set-CimInstance is to use a query. Interestingly enough, this WQL query is the same type of query that would have been used back in the VBScript days. The query to retrieve the network adapter named Ethernet appears here: "Select * from Win32_NetworkAdapter where NetConnectionID = 'EtherNet'" To assign a new value for a property, I use a hashtable. The hashtable specifies the property and the new value for the property. The hashtable to specify a value of RenamedConnection for the NetConnectionID property appears here: @{NetConnectionID="RenamedConnection"} The complete Set-CimInstance command appears here (this is a single line command) Set-CimInstance-Query"Select * from Win32_NetworkAdapter where NetConnectionID = 'EtherNet'"-Property @{NetConnectionID="RenamedConnectionUD = 'EtherNet'"-Property @{NetConnectionID="RenamedConnectionUD = 'EtherNet'"-Property @{NetConnectionID="RenamedConnectionUD = 'EtherNet' - Property @{NetConnectionID = 'EtherNet' - Prope

command (wrapping in the Windows PowerShell console) and the fact that there is not output from the command. On my Windows 8.1 laptop, I use the Get-NetAdapter command to verify that the adapter renamed.

image033.png

Using the NetAdapter module

Renaming a network adapter via Windows PowerShell requires admin rights. Unfortunately, the help does not mention this. You just have to sort of know this. Luckily, an error occurs when attempting to run the command without admin rights. The error is instructive, and informs that access is denied. The error appears here.

image035.png

The good thing is that the _access denied _error appears - some cmdlets do not display output, and do not let you know that you need admin rights to obtain the information (The Get-VM cmdlet is one of those. It returns no virtual machine information, but it does not generate an error either. This

situation is also true with the Start-VM cmdlet – does not do anything, but does not generate an error if you do not have rights).

So I close the Windows PowerShell console, right click on the Windows PowerShell console icon I created on my task bar, and run Windows PowerShell as Administrator. I now run the command to rename my network adapter with the _whatif _parameter to ensure it accomplishes what I want. Here is the command I use: "" Get-NetAdapter -Name Ethernet | Rename-NetAdapter -NewName Renamed -whatif

What if: Rename-NetAdapter -Name 'Ethernet' -NewName 'Renamed' That is exactly what I want to happen. I now use the up arrow, and remove the _whatif. _Here is the command (no output returns from this command). Get-NetAdapter -Name Ethernet | Rename-NetAdapter -NewName Renamed "" The command, and associated output appear in the figure here.




image037.png

I can modify my command just a bit, and return an instance of the renamed network adapter. To do this, I use the -passthru parameter from the Rename-NetAdapter function. One reason to do this is to see visual confirmation that the command completed successfully. Other reasons, would be to use the returned object to feed into other cmdlets and to perform other actions. Here is the revised command, showing how to use -passthru Get-NetAdapter -Name Ethernet | Rename-NetAdapter -NewName Renamed –PassThru The command, and associated output appear in the figure that follows.

image039.png

One of the really powerful things about the Get-NetAdapter function is that I can use wildcard

characters for the name parameter. This means that if I do not want to type the entire network adapter name, I can shorten it. It also means that if I have a similar naming pattern, I can use a wildcard pattern to retrieve them as well. Here is an example of using a wildcard. Get-NetAdapter -NameEther* This command works the same as the other commands, and therefore I can pipeline the results to the Rename-NetAdapter function. This technique appears here: Get-NetAdapter -Name Ether* | Rename-NetAdapter -NewName Renamed -PassThru As seen in the figure here, the command works perfectly.

image041.png

Finding connected network adapters

One of the most fundamental pieces of troubleshooting or security checks to do is to find out which of the many network adapters on a computer are actually connected to a network.

PowerTip : Show 'up' physical adapters

Question: You want to see which physical network adapters on your Windows 8.1 computer using Windows PowerShell. How can you do this?

Answer: Use the -physical parameter with the Get-NetAdapter function and filter for a status of up. This technique appears here: Get-NetAdapter -physical| where status -eq 'up' ## Using NetSh

It is pretty easy to use NetSh to retrieve information about the connection status of network adapters. To do so, I use the following command: netsh interface ipv4 show interfaces. One of the problems, from a management perspective, is that the command returns text. Therefore, if I need to parse the text to pull out specific information, such as the Interface Index number, or the Name of the adapter, then I am going to have to resort to writing a complicated regular expression pattern. If all I need to do is to obtain the information because I am writing to a log file as text, then the command works great, and is the lowest common denominator - I can use it all the way back to Windows 2000 days.

I can even run the netsh commands from within the Windows PowerShell console. This appears in the figure that follows.

	Administrator: Windows PowerShell				_ 🗆 x
PS C:\> netsh interface ipv4 show interfaces					^
Idx	Met	MTU	State	Name	
1 12 19	50 10 5	4294967295 1500 1500	connected connected connected	Loopback Pseudo-Interface 1 VEthernet (externalSwitch) VEthernet (internalSwitch)	
PS C:\	\> _				
					~

image043.png

Using WMI

It is possible to use WMI and the Win32_NetworkAdapter WMI class to retrieve information about the connection status. The NetConnectionStatus property reports backed in a coded value that

reports the status. These values are documented on MSDN for the Win32_NetworkAdapter class¹³. Using the Get-WmiObject Windows PowerShell cmdlet, I can work with any operating system that installs Windows PowerShell. This includes Windows XP, Windows Server 2003 and above. The following command returns information similar to the NetSh command. get-wmiobject win32_-networkadapter|select netconnectionid, name, InterfaceIndex, netconnectionstatus The command and the output from the command appear in the figure that follows. ![image045.png](images/image045. The difference is that instead of plain text, the command returns objects that can be further manipulated. Therefore, while the above command actually returns the network connection status of all network adapters, the NetSh command only returns the ones that are connected. If I filter on a netconnectionstatus of 2 I can return only the connected network adapters. The command becomes this one (this is a single line command that I broke at the pipeline character for readability): "" get-wmiobject win32 networkadapter -filter "netconnectionstatus = 2"

selectnetconnectionid,name,InterfaceIndex,netconnectionstatus "" The command and output appear in the figure that follows.

image047.png

If the desire is to obtain the connection status of more than just network adapters that are connected, then the task will require writing a script to do a lookup. The lookup values appear in the table that follows:

Value	Meaning
0	Disconnected
1	Connecting
2	Connected
3	Disconnecting
4	Hardware not present
5	Hardware disabled
6	Hardware malfunction
7	Media disconnected
8	Authenticating
9	Authentication succeeded
10	Authentication failed

¹³http://msdn.microsoft.com/en-us/library/aa394216%28v=vs.85%29.aspx

Value	Meaning
11	Invalid Address
12	Credentials required

The Get-NetworkAdapterStatus.ps1 script requires at least Windows PowerShell 2.0 which means that it will run on Windows XP SP3 and above.

Get-NetworkAdapterStatus.Ps1 "" <#

.Synopsis Produces a listing of network adapters and status on a local or remote machine.

.Description This script produces a listing of network adapters and status on a local or remote machine.

.Example Get-NetworkAdapterStatus.ps1 -computer MunichServer Lists all the network adapters and status on a computer named MunichServer

.Example Get-NetworkAdapterStatus.ps1 Lists all the network adapters and status on local computer

.Inputs [string]

.OutPuts [string]

.Notes NAME: Get-NetworkAdapterStatus.ps1

AUTHOR: Ed Wilson LASTEDIT: 1/10/2014

KEYWORDS: Hardware, Network Adapter

.Link

Http://www.ScriptingGuys.com

Requires -Version 2.0

>

Param([string]\$computer=\$env:COMPUTERNAME) #end param

```
functionGet-StatusFromValue { Param($SV) switch($SV) { 0 { " Disconnected" } 1 { " Connecting" } 2 { " Connected" } 3 { " Disconnecting" } 4 { " Hardware not present" } 5 { " Hardware disabled" } 6 { " Hardware malfunction" } 7 { " Media disconnected" } 8 { " Authenticating" } 9 { " Authentication succeeded" } 10 { " Authentication failed" } 11 { " Invalid Address" } 12 { " Credentials Required" } Default { "Not connected" } }
```

} #end Get-StatusFromValue function

*** Entry point to script ***

Get-WmiObject-Classwin32_networkadapter-computer\$computer

EXPRESSION={Get-StatusFromValue\$_.NetConnectionStatus}} If my environment is Windows 7 and Windows Server 2008 R2, I can use either Windows PowerShell 3.0 or Windows PowerShell 4.0. The advantage here, is that I gain access to the Get-CimInstance cmdlet which uses WinRM for remoting instead of DCOM that the Get-WmiObject cmdlet uses. The only change to the Get-NetworkAdapterStatus.ps1 script that is required is to replace the Get-WmiObject line with Get-CimInstance. The revision appears here: #*** Entry point to script ***

 $Get-CimInstance-Classwin 32_network adapter-computer \$ computer \$ Select-Object Name, @ \{LABEL="Status"; network adapter-computer"\} = (ABEL="Status"; network adapter-computer") = (ABEL="Status") = (A$

EXPRESSION={Get-StatusFromValue\$_.NetConnectionStatus}} "" When I run the Get-StatusFromValue.ps1 script, in the Windows PowerShell ISE, I see the output achieved here.

*** Entry point to script ***




image049.png

Using the NetAdapter module

On Windows 8 and above the NetAdapter module contains the Get-NetAdapter function. To see the status of all network adapters, use the Get-NetAdapter function with no parameters. The command appears here: Get-NetAdapter The output from this command appears here.

	Administrator: Windows PowerShell		_ 🗆	X
PS C:\> Get-NetAdapter				^
vEthernet (internalSwi vEthernet (WiFiExterna vEthernet (externalSwi	InterfaceDescription Intel(R) 82579LM Gigabit Network Con Hyper-V Virtual Ethernet Adapter #4 Hyper-V Virtual Ethernet Adapter #3 Hyper-V Virtual Ethernet Adapter #2	19 16 12	Up Up Disabled Up	ĺ
	Intel(R) Centrino(R) Ultimate-N 6300 Bluetooth Device (Personal Area Netw		Disabled Disabled	V

image051.png

I can reduce the output to only physical adapters by using the -physical parameter. This command appears here. Get-NetAdapter-Physical If I only want to see the physical network adapters that are actually up, I pipeline the results to the where-object. This command appears here. Get-NetAdapter-physical|wherestatus-eq'up' The commands and the output from the two previous commands appear in the figure that follows.




image053.png

Network Adapter power settings

Beginning with Windows 7, the network adapter power settings expanded¹⁴. Some of the improvements are listed here:

- Wake on LAN and Wake on Wireless LAN. Improved wake patterns reduce the number of false wakes. Beginning with Windows 7 a directed packet (such as a ping) does not cause the computer to wake up.
- ARP (Address Resolution Protocol) and NS (Neighbor Solicitation) offload. ARP and NS packets
 do not wake up the computer. Instead the network adapter, beginning with Windows 7, can
 respond. Therefore the computer does not need to wake up just to maintain a presence on the
 network. This support depends on at least NDIS 6.0 drivers and may not be available with older
 hardware.
- Low Power on Media Disconnect. Enables the computer to place the network adapter into a low power state when the network cable is unplugged and the computer is running.

These settings are configurable via the graphical user interface by selecting the configure button from the network adapter properties dialog box. The settings appear in the figure that follows.

 $^{^{14}} http://technet.microsoft.com/en-us/library/ee617165 (v=WS.10).aspx$




image055.png

PowerTip: Get network adapter power management settings

Question: You want to get the network adapter power management settings on your Window 8.1 computer. How can you use Windows PowerShell to do this?

Answer: Use the Get-NetAdapterPowerManagement function and specify the name of the network adapter to query. Get-NetAdapterPowerManagement-Name ethernet

Using NetSh

Some of the network adapter power management settings are configurable via NetSh. For example, to permit ARP packets and NS packets to wake the network adapter, I would use a command such as the following: netsh interface ipv4 set interface 12 forcearpndwolpattern=enabled When the command completes successfully, it returns OK. Keep in mind, this will also cause a network adapter reset. The command and associated output appear here:




image057.png

Using the NetAdapter module

To query the power management settings for a specific network adapter, use the Get-NetAdapterPowerManagement function and specify the name of the network adapter. An example of the command appears here:

Get-NetAdapterPowerManagement -Name ethernet The command, and the output associated with the command appear in the figure that follows.




image059.png

The Get-NetAdapterPowerManagement function only permits the use of the adapter name or interface description as parameters. But the Get-NetAdapter function is much more flexible. I often use Get-NetAdapter to retrieve a specific network adapter and then pipeline it to other functions such as Get-NetAdapterPowerManagement. This technique appears here: Get-NetAdapter -Interface Index4 | Get-NetAdapterPowerManagement To configure the network adapter power management, I use the Set-NetAdapterPowerManagement function. Once again, I want to retrieve my network adapter by interface index number instead of having to type the name or description of the adapter. I pipeline the resulting network adapter object to the Set-NetAdapterPowerManagement function and specify a value for the -WakeOnMagicPacket parameter. The command appears here. Get-NetAdapter -Interface Index4 | Set-NetAdapterPowerManagement -WakeOnMagicPacket Enabled Because no output returns from the command, I use the Get-NetAdapter command a

second time to verify the configuration change took place. The commands and associated output appear in the figure that follows.

```
_ 🗆
                                Administrator: Windows PowerShell
PS C:\> Get-NetAdapter -InterfaceIndex 4 | Set-NetAdapterPowerManagement -WakeOnMagic >
Packet Enabled
PS C:\> Get-NetAdapter -InterfaceIndex 4 | Get-NetAdapterPowerManagement
InterfaceDescription
                         : Intel(R) 82579LM Gigabit Network Connection
Name
                          Ethernet
ArpOffload
                         : Disabled
NSOffload
                         : Disabled
RsnRekeyOffload
                         : Unsupported
D0PacketCoalescing
                         : Unsupported
SelectiveSuspend
                         : Unsupported
DeviceSleepOnDisconnect : Disabled
WakeOnMagicPacket
                         : Enabled
WakeOnPattern
                         : Disabled
PS C:\>
```

image061.png

Now, it so happens that I know what the permissible values are for the parameters. But if I did not know this, I could create the command in the Windows PowerShell ISE and rely upon the intellisense features. When I type a parameter name, the permissible values appear and make it possible to select the correct value from the list. This appears in the figure that follows.




image063.png

Most of the times, when I need to manage network adapter power management settings, it is because of a new deployment, or because an audit has determined that I have configuration drift. (Hmmm - this would actually be a great thing to use Desired Configuration Management to control.) So, what I do is put all the settings I want to configure into a single command. Such a command appears here: "" Set-NetAdapterPowerManagement -Name ethernet -ArpOffload Enabled -DeviceSleep OnDisconnect Disabled -NSOffload Enabled -WakeOnMagicPacket Enabled

-WakeOnPattern Enabled -PassThru

"" The -passthru parameter outputs a configuration management object so that I can inspect it and ensure that the proper things change that I wanted changed. The command, and the output from the command appear in the figure that follows:




image065.png

To make changes to multiple computers, I first use the New-CimSession cmdlet to make my remote connections. I can specify the computer names and the credentials to use to make the connection. I then store the remote connection in a variable. Next, I pass that cimsession to the -cimsession parameter. The key to remember here, is that I must be able to identify the network adapter that I need to use for the management activity. An example of creating a Cim Session and using it appears here (keep in mind this is a two line command. If you directly copy and paste this command you must change the computer name, network interface name, and remove spaces until the second command appears on a single line). \$session = New-CimSession -ComputerName edlt Set-NetAdapterPowerManagement -CimSession \$session -name ethernet -ArpOffload Enabled -DeviceSleepOnDisconnect Disabled -NSOffload Enabled -WakeOnMagicPacket Enabled -WakeOnPattern Enabled -PassThru The command and the output from the command appear in the figure that follows.

```
Administrator: Windows PowerShell
PS C:\> $session = New-CimSession -ComputerName edlt
PS C:\> Set-NetAdapterPowerManagement -CimSession session -name ethernet -ArpOffload
 Enabled -DeviceSleepOnDisconnect Disabled -NSOffload Enabled -WakeOnMagicPacket Enab
led -WakeOnPattern Enabled -PassThru
                            : Intel(R) 82579LM Gigabit Network Connection
InterfaceDescription
Name
                              Ethernet
ArpOffload
                            : Enabled
NSOffload
                            : Enabled
RsnRekeyOffload
                            : Unsupported
DOPacketCoalescing
                            : Unsupported
SelectiveSuspend : Unsupported
DeviceSleepOnDisconnect : Disabled
WakeOnMagicPacket
                            : Enabled
WakeOnPattern
                            : Enabled
PSComputerName
                            : edlt
PS C:\>
```

image067.png

Keep in mind that these commands require that either the Windows PowerShell console or the Windows PowerShell ISE is opened with admin rights. To do this, right click on the Windows PowerShell console icon or Windows PowerShell ISE icon while holding down the shift key and select run as administrator. Or if you launch it via Windows Search on Windows 8.1 type Windows PowerShell from the Start page, and the Search dialog appears with the Windows PowerShell icon. Right click on the icon and select Run as Administrator from the action menu.

If you do not launch Windows PowerShell with admin rights, an error occurs stating that it cannot find the network adapter. An example of the error appears in the figure that follows.

```
PS C:\> Get-NetAdapterPowerManagement -Name ethernet
Get-NetAdapterPowerManagement : No MSFT_NetAdapterPowerManagementSettingData
objects found with property 'Name' equal to 'ethernet'. Verify the value of the
property and retry.
At line:1 char:1
+ Get-NetAdapterPowerManagement -Name ethernet
+ CategoryInfo : ObjectNotFound: (ethernet:String) [Get-NetAdapterPowe
rManagement], CimJobException
+ FullyQualifiedErrorId : CmdletizationQuery_NotFound_Name,Get-NetAdapterPowerM
anagement

PS C:\>
```

image069.png

One of the cool things about the Windows platform are all the different ways of obtaining networking statistical information. There are things like NetStat, NetSh, performance counters, as well as the Get-NetworkStatistics function from the NetAdapter Windows PowerShell module. All of these methods can be used inside the Windows PowerShell console, or from within the Windows PowerShell ISE.

PowerTip: Use PowerShell to find Networking counters

Question: You need to check on the network performance, but do not know where to begin. How can you use Windows PowerShell to find networking counters?

Answer: Use the Get-Counter cmdlet and the -ListSet parameter. Select the CounterSetName property and filter on names related to networking. The following command returns sets related to IPV6. Get-Counter -ListSet * | select countersetname | where countersetname -match 'ipv6' ## NetSh

Using NetSh to obtain network statistics is easy and powerful. For example to show IP statistics, I use the command appearing here. netsh interface ipv4 show ipstats. A sample output from this command appears in the figure that follows.




image071.png

To show TCP statistics using NetSh, I use the command appearing here. netsh interface ipv4 show tepstats The command, and the output from the command appear in the figure that follows.




image073.png

One of the cool things about using NetSh from within Windows PowerShell is that I have the power of Windows PowerShell at my fingertips. Rather than keep going back and forth to find stuff, I can pipeline the results from a command to the Select-String cmdlet. For example, if I am interested in how many commands are available to show statistics, I use the command appearing here because I noticed that each of the commands contains the letters stats: netsh interface ipv4 show | Select-String "stats" The output from the command appears here: "" PS C:> netsh interface ipv4 show | Select-String "stats"

show icmpstats - Displays ICMP statistics.

show ipstats - Displays IP statistics.

show tepstats - Displays TCP statistics.

show udpstats - Displays UDP statistics. In addition to the IPV4 interface, I can also work with the IPV6 interface and obtain similar statistics. Here is the command I used to obtain that information: PS C > netsh interface ipv6 show | Select-String "stats"

show ipstats - Displays IP statistics.

show tepstats - Displays TCP statistics.

show udpstats - Displays UDP statistics. In addition to using the Select-String cmdlet to parse the output from the NetSh help, I can also use it to hone in on specific information from the statistics. For example, the following command retrieves IPv6 interface IP stats. netSh interface ipv6 show ipstats I can hone in on the output and look

for errors by piplining the results to the Select-String cmdlet and choosing error. This command appears here. netsh interface ipv6 show ipstats | Select-String errors "" In the figure that follows, I first show the command to retrieve the IPV6 IP statistics. Next I show the output from the command. Then I filter the output to only errors by using the Select-String cmdlet and lastly, I show the output from the filtered string.

```
_ 🔳 ×
                               Select Administrator: Windows PowerShell
PS C:\> netsh interface ipv6 show ipstats
MIB-II IP Statistics
Forwarding is:
                                       Disabled
Default TTL:
                                       128
In Receives:
                                       9508
In Header Errors:
In Address Errors:
                                       4549
Datagrams Forwarded:
In Unknown Protocol:
                                       3549
In Discarded:
In Delivered:
                                       7926
Out Requests:
                                       22012
Routing Discards:
                                       0
Out Discards:
                                       0
Out No Routes:
Reassembly Timeout:
Reassembly Required:
Reassembled Ok:
                                       Ō
Reassembly Failures:
Fragments Ok:
Fragments Failed:
Fragments Created:
PS C:\> netsh interface ipv6 show ipstats | Select-String errors
In Header Errors:
                                       4550
In Address Errors:
PS C:\>
```

image075.png

NetStat

The NetStat command has been around in the Windows world for a long time. It provides a quick snapshot of connections from local ports to remote ports as well as the protocol and the state of those connections. It takes a couple of minutes to run, and as a result it makes sense to store the results of NetStat into a variable. I can then examine the information several times if I wish without having to wait each time to gather the information additional times. Here is an example of running the NetStat command and storing the results from in a variable. \$net=NetStat To display the information in an unfiltered fashion, I just type \$net at the Windows PowerShell prompt and it displays all of the information that it gathered. Here is an example: \$net The command to run NetStat and store the results in a variable as well as to examine the contents of the \$net variable appear in the figure that follows.

```
_ 🗆
                                     Administrator: Windows PowerShell
PS C:\> $net = NetStat
PS C:\> $net
Active Connections
                                                                  State
  Proto
           Local Address
                                      Foreign Address
                                      199.16.156.231:https
199.16.156.231:https
           192.168.0.42:58232
                                                                  CLOSE_WAIT
  TCP
  TCP
           192.168.0.42:58233
                                                                  CLOSE_WAIT
           192.168.0.42:58234
  TCP
                                      93.184.216.139:https
                                                                  CLOSE_WAIT
          192.168.0.42:58863
192.168.0.42:58864
  TCP
                                      a23-3-173-199:https
                                                                  ESTABLISHED
                                      a23-3-173-199:https
  TCP
                                                                  ESTABLISHED
  TCP
           192.168.0.42:58865
                                      a23-3-173-199:https
                                                                  ESTABLISHED
                                      64.53.32.64:http
64.53.32.64:http
  TCP
           192.168.0.42:58867
                                                                  ESTABLISHED
  TCP
           192.168.0.42:58868
                                                                  ESTABLISHED
  TCP
                                      a23-3-173-199:http
           192.168.0.42:58869
                                                                  ESTABLISHED
                                      64.53.32.65:http
64.53.32.65:http
  TCP
           192.168.0.42:58870
                                                                  ESTABLISHED
  TCP
           192.168.0.42:58871
                                                                  ESTABLISHED
  TCP
           192.168.0.42:61257
                                      bn1wns1011516:https
                                                                  ESTABLISHED
  TCP
TCP
          192.168.0.42:61698
192.168.0.42:61700
                                      edge-star-shv-12-iad1:https
edge-star-shv-12-iad1:https
                                                                         CLOSE_WAIT
                                                                         CLOSE_WAIT
  TCP
           192.168.0.42:61701
                                      edge-star-shv-12-iad1:https
                                                                         CLOSE_WAIT
                                                                         CLOSE_WAIT
  TCP
TCP
           192.168.0.42:61702
192.168.0.42:61703
                                      edge-star-shv-12-iad1:https
                                      edge-star-shv-12-iad1:https
  TCP
                                      64.53.32.155:https
           192.168.0.42:61704
                                                                  ESTABLISHED
                                      a184-26-142-154:https
a184-26-142-154:https
  TCP
          192.168.0.42:61705
192.168.0.42:61706
                                                                  ESTABLISHED
  TCP
                                                                  ESTABLISHED
  TCP
                                      edge-star-shv-12-iad1:https
           192.168.0.42:61707
                                                                         CLOSE_WAIT
  TCP
           192.168.0.42:61708
                                      edge-star-shv-12-iad1:https
                                                                         CLOSE_WAIT
  TCP
           192.168.0.42:61709
                                                                         CLOSE_WAIT
                                      edge-star-shv-12-iad1:https
  TCP
           192.168.0.42:61710
                                      edge-star-shv-12-iad1:https
                                                                         CLOSE_WAIT
  TCP
          192.168.0.42:61711
192.168.0.42:61712
                                      edge-star-shv-12-iad1:https
                                                                         CLOSE_WAIT
                                                                         CLOSE_WAIT
  TCP
                                      edge-star-shv-12-iad1:https
  TCP
           192.168.0.42:61713
                                      a184-26-142-131:https ESTABLISHED
           192.168.0.42:61714
192.168.0.42:61715
                                      a184-26-142-131:https
64.53.32.25:https
  TCP
                                                                  ESTABLISHED
  TCP
                                                                  ESTABLISHED
  TCP
           192.168.0.42:61716
                                      a184-26-136-97:https
                                                                  ESTABLISHED
           192.168.0.42:61717
192.168.0.42:61719
                                                                        CLOSE_WAIT
  TCP
                                      xx-fbcdn-shv-05-iad1:https
                                      xx-fbcdn-shv-05-iad1:https
  TCP
  TCP
           192.168.0.42:61720
                                      xx-fbcdn-shv-05-iad1:https
                                                                        CLOSE_WAIT
  TCP
                                      64.53.32.138:https
64.53.32.155:https
           192.168.0.42:61721
                                                                  ESTABLISHED
           192.168.0.42:61722
                                                                  ESTABLISHED
  TCP
  TCP
           192.168.0.42:61723
                                      xx-fbcdn-shv-04-iad1:https CLOSE_WAIT
                                                                  SYN_SENT
  TCP
           192.168.0.42:63662
                                      192.168.0.47:9100
PS C:\>
```

image077.png

The real power, however, comes in using Windows PowerShell to parse the text output to find specific information. For example, the previous output shows multiple connections in various states of connectiveness. I can easily parse the output and find only the connections that are Established. The command I use appears here. <code>\$net|select-string "Established"</code> The command and the output from the command appear in the figure that follows.




image079.png

Interestingly enough, I can also use NetSh to report on TCP connections. The command appears here: netsh interface ipv4 show topconnections. The output from the command, as appears in the figure that follows, is a bit different than that received from NetStat.

		Administrator: Window			_ 🗆 🗙
PS C:\> netsh in	terface ipv4	show tcpconnection	S		^
MIB-II TCP Conne	ction Entry				
Local Address	Local Port	Remote Address	Remote Port	State	
0.0.0.0	135	0.0.0.0	0	Listen	
169.254.140.58	139	0.0.0.0	0	Listen	
	139	0.0.0.0	0	Listen	
0.0.0.0	554	0.0.0.0	0 0 0 0 0 0	Listen	
0.0.0.0	2179	0.0.0.0	0	Listen	
	2559	0.0.0.0	0	Listen	
0.0.0.0	49152	0.0.0.0	0	Listen	
0.0.0.0	49153	0.0.0.0	0	Listen	
0.0.0.0	49154 49155	0.0.0.0	0	Listen Listen	
0.0.0.0	49156	0.0.0.0	0	Listen	
0.0.0.0	49157	0.0.0.0	0	Listen	
0.0.0.0	49160	0.0.0.0	ŏ	Listen	
192.168.0.42	58232	199.16.156.231	443		
192.168.0.42	58233	199.16.156.231	443	Close Wait	
192.168.0.42	58234	93.184.216.139	443	Close Wait	
192.168.0.42	58863	23.3.173.199	443	Established	
192.168.0.42	58864	23.3.173.199	443	Established	
192.168.0.42	58865	23.3.173.199	443	Established	
192.168.0.42	58867	64.53.32.64	80	Established	
192.168.0.42	58868	64.53.32.64	80	Established	
192.168.0.42	58869	23.3.173.199	80	Established	
192.168.0.42	58870	64.53.32.65	80	Established	
192.168.0.42	58871	64.53.32.65	80	Established	
192.168.0.42	61257	157.56.98.92	443	Established	
192.168.0.42	61698	31.13.69.160 31.13.69.160	443	Close Wait	
192.168.0.42	61700	31.13.69.160	443	Close Wait Close Wait	
192.168.0.42 192.168.0.42	61701 61702	31.13.69.160	443 443	Close Wait	
192.168.0.42	61703	31.13.69.160	443	Close Wait	~
132.100.0.42	01/03	31.13.03.100	773	CIOSC Walt	· ·

image081.png

Performance Counters

To collect performance counter information, I need to know the performance counter set names so I can easily gather the information. To do this, I use the Get-Counter cmdlet and I choose all of the listsets. I then like to sort on the countersetName property and then select only that property. The following command retrieves the available listsets. "" Get-Counter -ListSet * | Sort-Object CounterSetName | Select-Object CounterSetName

If I pipeline the output to the Out-GridView cmdlet, then I can easily filter the list to find the listsets I wish to use. This command appears here. Get-Counter-ListSet * | Sort-Object CounterSetName | Select-Object CounterSetName | Out-GridView

"" The resulting Out-GridView pane makes it easy to filter for different values. For example, the figure that follows filters for IP.




image083.png

Once I have the countersetname value I wish to query, it is a simple matter of plugging it into the Get-Counter to first obtain the paths. This command appears here. \$paths = (Get-Counter -ListSet ipv4).paths Next I use the paths with the Get-Counter cmdlet to retrieve a single instance of the IPv4 performance information. The command appears here. Get-Counter -Counter \$paths The commands and the output from the commands appear in the figure that follows.

```
_ 🗆
                               Administrator: Windows PowerShell
PS C:\> $paths = (Get-Counter -ListSet ipv4).paths
PS C:\> Get-Counter -Counter $paths
Timestamp
                          CounterSamples
1/10/2014 7:19:38 AM
                          \\edlt\ipv4\datagrams/sec :
                          0.99843710564718
                          \\edlt\ipv4\datagrams received/sec :
                          \\edlt\ipv4\datagrams received header errors :
                          \\edlt\ipv4\datagrams received address errors :
                          \\edlt\ipv4\datagrams forwarded/sec :
                          \\edlt\ipv4\datagrams received unknown protocol :
                          \ \ \\edlivered/sec : 2.99531131694154
                          \\edlt\ipv4\datagrams sent/sec :
                          0.99843710564718
                          \\edlt\ipv4\datagrams outbound discarded :
```

image085.png

If I want to monitor a counter set for a period of time, I use the -SampleInterval property and the -MaxSamples parameter. In this way I can specify how long I want the counter collection to run. An example of this technique appears here. Get-Counter -Counter \$paths -SampleInterval 60 -MaxSamples 60 If I want to monitor continuously, until I type Ctrl-C and break the command, I use the -Continuous parameter and the -SampleInterval parameter. An example of this command appears here. Get-Counter -Counter \$paths -SampleInterval 30 -Continuous ## Using Get-NetAdapterStatistics function

The easiest way to gather network adapter statistics is to use the Get-NetAdapterStatistics function from the NetAdapter module. It provides a quick overview of the sent and received packets. An example of the command appears here. Get-NetAdapterStatistics The command and a sample output appear in the figure that follows.




image087.png

If I want to work with a specific network adapter I can use the name of the adapter, or for more flexibility I can pipeline the results from the Get-Netadapter function. This technique appears here. Get-NetAdapter -ifIndex 12| Get-NetAdapterStatistics The Get-NetAdapterStatistics function returns more than just bytes sent and received. To find the additional information I like to pipeline the results to the Format-List cmdlet. An example of this technique appears here. Get-NetAdapter -ifIndex 12| Get-NetAdapterStatistics | format-list* The command, and the output associated with the command appear in the figure that follows.




image089.png

Resources

Books from Microsoft Press

Windows PowerShell 3.0 First Steps¹⁵ - A Windows PowerShell primer providing an overview of the major Windows PowerShell components.

Windows PowerShell 3.0 Step by Step¹⁶ - A Windows PowerShell step by step learning guide, complete with lab exercises, review questions, and answers. This book contains hundreds of Windows PowerShell scripts.

Windows PowerShell Best Practices¹⁷ - The Windows PowerShell best practices guide, containing real world tips, gotchas, and techniques from hundreds of field personnel. The contributors include Microsoft Windows PowerShell developers, Microsoft Windows PowerShell MVP's, Enterprise network administrators, and top Dev-ops.

Web Resources

The Microsoft Script Center¹⁸ - dedicated to system administrator scripters the world over.

The Scripting Guys Forum¹⁹ - community forum for asking scripting questions.

The Script Center Script Repository²⁰ - the largest collection of admin scripts on the internet.

The Hey Scripting Guy Blog²¹ - thousands of blog articles about scripting. Updated twice a day, 365 days a year, it is the #1 blog on MSDN and on TechNet.

The Script Center Community Page²² - insight into Windows PowerShell community activities, especially activities where the Microsoft Scripting Guy and the Scripting Wife will appear.

The Script Center Learn PowerShell Page²³ - central hub for learning about Windows PowerShell.

NetAdapter module documentation²⁴ - official Microsoft documentation for the NetAdapter module from TechNet.

PoshCode²⁵ - Windows PowerShell community driven script repository.

 $^{^{15}}http://www.amazon.com/Windows-PowerShell-3-0-First-Steps/dp/0735681007/ref=sr_1_3?s=books\&ie=UTF8\&qid=1389394686\&sr=1-3\&keywords=ed+wilson$

 $^{^{16}} http://www.amazon.com/Windows-PowerShell-3-0-Step/dp/0735663394/ref=sr_1_1?s=books\&ie=UTF8\&qid=1389394766\&sr=1-128epwords=ed+wilson$

 $^{^{17}}http://www.amazon.com/Windows-PowerShell-Best-Practices-Wilson/dp/0735666490/ref=sr_1_2?s=books\&ie=UTF8\&qid=1389394813\&sr=1-2\&keywords=powershell+best+practices$

¹⁸http://technet.microsoft.com/en-us/scriptcenter

¹⁹http://social.technet.microsoft.com/Forums/en/category/scripting

²⁰http://gallery.technet.microsoft.com/scriptcenter

²¹http://blogs.technet.com/b/heyscriptingguy/

²²http://technet.microsoft.com/en-us/scriptcenter/hh182567.aspx

²³http://technet.microsoft.com/en-us/scriptcenter/dd742419.aspx

²⁴http://technet.microsoft.com/en-us/library/jj134956.aspx

²⁵http://poshcode.org/

69 Resources

PowerShell.Org²⁶ - Windows PowerShell community site containing blogs, forums, user group information and a script repository.

PowerShellGrroup.org²⁷ - listing of Windows PowerShell community user group meetings.

PowerShellSaturday.Org²⁸ - listing of Windows PowerShell Saturday community events.

²⁶http://powershell.org/wp/

²⁷http://powershellgroup.org/ 28http://powershellsaturday.com/welcome/